LID1265 ToolBox Installation and User Guide



LID1265

DATE: 26-January-2021

Contents:

1.	Introduction	3
2.	Requirements	3
3.	General description of the LID1265 decoder	3
4.	How to install the software on your computer	4
5.	How to use the LID1265 ToolBox software for upload and downloading data	12

1. Introduction

This manual contains the installation and user instructions for the LID1265 ToolBox software. The following topics are covered:

- Requirements
- General description of the LID1265 decoder
- How to install the software
- How to upload and download custom names to the LID1265 decoder

2. Requirements

The LID1265 ToolBox software requires a PC with the following components installed:

- Microsoft Windows XP, 7, 8 10
- Microsoft Office 2007/2010 or above
- RS232 serial port (or an installed USB to RS232 converter) or USB port
- LID1265 decoder

3. General description of the LID1265 decoder

The LID1265 decoder is a stationary decoder which contains a 2x16 characters LCD. The readers internal memory makes it possible to store a list of known Transponder codes with a user defined custom name. Once a known code was read, the LID1265 is displayed the assigned custom name. Port 4 will accommodate a connection from any of the Dorset antennae (ANT610,611,613). Communication can be by either USB Port 1 or Serial Port 2



4. How to install the software on your computer

This topic guides you through the installation process.

Start the LID1265 ToolBox setup executable.

Accept the agreement and click [next] to continue.

License Agreement Please read the following important information before continuing.		L.
Please read the following important information before continuing.		514
Please read the following License Agreement. You must accept the term agreement before continuing with the installation.	ns of this	
Dorset ID License.txt for Licensed Copies of Dorset ID Products Copyright 1997-2015 by Dorset ID b.v. All Rights Reserved.		^
Thank you for using Dorset ID products. This file provides details regarding your product license. For product-specific information please refer to the program itself.		
PRODUCT LICENSE AGREEMENT		
NOTICE TO USERS: CAREFULLY READ THE FOLLOWING LEGAL		~
• I accept the agreement		
○ I <u>d</u> o not accept the agreement		
Next >		Cancel

Setup - LID1265 Toolbox		10/22	- 🗆
Select Start Menu Folder Where should Setup place th	e program's shortcuts?		P1
Setup will create the	e program's shortcuts in	n the following Start I	Menu folder.
Dorset ID/LID1265	ou would like to select a		Browse
	\backslash		
		\mathbf{n}	

Check both boxes, click [next] to continue.

🔂 Setup - LID1265 Toolbox	-		×
Select Additional Tasks			
Which additional tasks			
which additional tasks should be performed?		(
Select the additional tasks you would like Satur to perform while in	talling I II	01265	
Toolbox, then dick Next.		01205	
Create shortcuts for all files in startment			
Create shortcuts to all files on deskton			
< <u>B</u> ack <u>N</u> e	xt >	Can	icel





Click [next] to continue

Click [next] to continue



Click [Finish]



If the system has no Microsoft .NET framework 4 installed, the wizard will ask to install it. This is required to run the software. If this popup appears, an internet connection is required to download the Microsoft .NET framework 4 installer.

Click [yes]



The setup is downloading the Microsoft .NET framework 4, please wait until the download is completed.

Setup - LID1265 Custom names uploader	<u> </u>
Ready to Install Setup is now ready to begin installing LID1265 Custom names uploader on you computer.	JI D
Click Install to continue with the installation, or click Back if you want to review change any settings.	v or
Download dependencies: .NET Framework 4.0	<u></u>
Install dependencies: .NET Framework 4.0	
Destination location: C:\Program Files\Dorset ID\LID1265 Custom names uploader	
Start Menu folder: Dorset ID\LID1265	
र	▼ ►
< Back Install	Cancel

After downloading the Microsoft .NET framework 4, the setup will extract the required files, please wait until the extraction is completed

File:	dotNetEx40 Full setup.exe(1 of 1)	
Speed:	1 KB/s	
Status:	Receiving	
Elapsed Time:	0:00:01	
Remaining Time:	0:14:27	
Current File:		1 KB of 868 KB (0%)
Overall Progress:		1 KB of 868 KB (0%)
1		

After downloading the Microsoft .NET framework 4, the setup will extract the required files, please wait until the extraction is completed.

Extracting files	×
Preparing: C:\5a1587da5eecf98f16fb12\;	1032\LocalizedData.xml
	Cancel

Accept the license agreement and click on install to continue. Microsoft .NET framework 4 is installing on the system, please wait

<u>Please note: if you do not have SQLSERVER EPRESS software installed on your computer,</u> <u>you will have to link to https://go.microsoft.com/fwlink/?linkid=866658</u> <u>and install the free SQLSERVER EPRESS software. This is required for the Download</u> <u>Custom Names application</u>

5. How to use the LID1265 Custom names uploader software

Make sure the 1265 is mains connected and communicating with the computer by USB or Serial port.



2. Select Next



3. Click on Open File

 LID1265 Custom names uploader V1.0.2 Preparation Select file to upload 	<u>81</u>	□ ×
Open file		U
	< Back	Nexto

4. Find the file you wish to upload and Select Open (the file should be CSV or xls...)

rganize 🔻 🛛 New folde	r			
📙 Reader Instructic ^	Name	Nate modified	Туре	Size
oneDrive	1265testfile.xls	1/5/2021 7:47 AM	Microsoft Office E	19 KB
This PC				
3D Objects		\backslash		
		`		
Desktop		$\langle \rangle$		
Desktop				
Desktop Documents Complete				
 Desktop Documents Downloads Music 				
Desktop Documents Downloads Music Pictures				
Desktop Documents Downloads Music Pictures Videos			\	
 Desktop Documents Downloads Music Pictures Videos OS (C:) 				
 Desktop Documents Downloads Music Pictures Videos OS (C:) Local Disk (D:) 				
 Desktop Documents Downloads Music Pictures Videos OS (C:) Local Disk (D:) HP_RECOVERY (

5. Select Next

	Sel	ect sheet: Sheet	t1	¥	
	Trovan Unique	0007BBF2ED	test-01		
Þ	Trovan Unique	0006E3BB07	test-82		
	Trovan Unique	00072AAF85	test-03		
	Trovan Unique	0007B816D6	test-04		
	Trovan Unique	00072A95CB	test-05		
	Trovan Unique	00072AB82D	test-07		
	Trovan Unique	00072674A1	test-08		

Required column name	Selected column
Transponder type	Trovan Unique
Transponder code	0007BBF2EQ
Custom name	test-01

Required column name	Selected column
ransponder type	Trovan Unique
ransponder code	0807BBF2ED
lustom name	test-01

7. Select Yes to Overwrite or No to append to the existing file

Question			×
?	Do you wish to overwrite the record	ds that are already in the LID1.	265 decoder?
	If you select NO, records will be ac	Ided. In case of a duplicate rec	cord you will be warned.
	Yes	No	

8.	Sel	ect	ОК
----	-----	-----	----

8. Select OK		
	LID1265 Tool Box Custom Names Documentation rev 1.doc [Compatibility Mode] - Microsoft Word non-commercial use	- 5 X
Rester Memory Maintenance	LID1265 toolbox V1.0.1.0	× .
Pate Custom manes Usload Custom names Custom names		DORSET ID IDENTIFICATION
	Image: Cursto mannes spisader V1.0.2 Image: Cursto mannes Marker Image: Cursto mannes Marker Image: Cursto mannes Marker Image: Cursto mannes Image: Cursto mannes Ima	
Page: 4 of 7 Words: 68 🧭		

The custom names file has been successfully uploaded

Instructions on using LID1265 Toolbox Program for Custom Names DOWNLOAD

- 1. Select Download Custom Names

2. Select Start Download



3. Select Yes or NO



4. Select Save to a File

				LID1265 toolbox V1.0.1.0		-
Reader Memory Maintenance	<u> </u>					
Custom names Upload Usedom Custom names						DORSET I
		1265 Custom names dow Custom names Page Castom Custom Transponder type Trovan Unque Trovan Unque	oder downloader controls Skett downloader oorsolader oodeselbare 0006810F48 0006810F48 0006810F48 0006810F48 0006810F48 0006810F48 0006800F48 0006800F48 0006800F48 0006800F48 0006800F48 0006800F41 0006800F41 0006800F41 0006800F41 00067677628 00067677628 0006800D41 00067677628 00067774 0006800D41 00067774 0006800D42 00067774 0006800D42 00067774	Save to file Custom name CRL-026 CRL-026 CRL-028 Wayne test-1 CRL-028 Wayne test-1 CRL-029	(Information) Available records in decoder:	

- 5. Give the file a name. Select Save 00 Save As X $\leftarrow \rightarrow \infty$ ↑ 🧧 « Microchip ID → Instructions → 2021 → Test File Ō ×. • ? Organize 🔻 New folder Name Date modified Туре Size This PC 1265testfile.xls 1/5/2021 7:47 AM Microsoft Office E... 19 KB 3D Objects 1265testfile.xlsx 1/18/2021 10:42 AM Microsoft Office E... 9 KB E Desktop test.xls 1/25/2021 12:34 PM Microsoft Office E ... 12 KB 🗄 Documents 🕹 Downloads Music Pictures Videos 🚛 OS (C:) 🕳 Local Disk (D:) - HP_RECOVERY (Network File name: LID1265 test file v Save as type: Excel, CSV or text files (*.xls;*.xlsx;*.csv;*.txt) Ŷ Save Cancel ∧ Hide Folders

6. Select OK Vou have saved this data

Reader Memory Maintenance	
Image: Sector	